



Big White Duck

**We're OBSESSED
with CREATING Awesome
STACKS**



TOPBAR JOEY

Website: www.bigwhiteduck.com

Email: support@bigwhiteduck.com

Joey – Settings

Create Launcher?

- Will enable a Joey Launcher to open Dropdown Content

Create Main Content?

- Joey will create a stacks dropzone for Main Content to be injected in to the TopBar below the menu items

Create Scroll Content?

- Joey will create a stacks dropzone for Scroll Content to be injected in to the TopBar below the menu items

Joey – Launcher

Launcher Type

- Joey
 - This is a general button type launcher that can easily be customized to match TopBars built in menus.
 - Note: You may need to apply Top Padding to the Joey stack to align the Luancher with other TopBar menu Items
- ButtonPlus
 - Drop a ButtonPlus button into Joeys Launcher dropzone.
 - You must set the ButtonPlus type to Joey Launcher
 - Make styling adjustments in the ButtonPlus settings NOT in the Joey Launcher settings
- Image
 - You can select between one image or two images – one for when Joey’s Content is open and one for when it is collapsed.

Size

If the launcher is used in TopBar’s extra zone, ensure that it is not too big. If it is taller than the TopBar then it will overflow and create wrapping of the content added to Joeys Main Content Area.

A setting of tiny works with a standard 45px high TopBar.

Launch Mode

- Click
 - Display of Joeys’ Main Content is toggled by clicking the Launcher
 - Display of Joeys’ Main Content is toggled by hovering over the Launcher

Launcher Style Settings

- These should be self explanatory.
 - If you want a button-less text link for TopBar simply set the Opacity to 0%

Joey – Main Content

Start Expanded

- The Main Content area will be in the expanded or shown state when the page loads. If you want permanent Main Content, then select this setting and do not create a Launcher.

Reveal Speed

- The time in milliseconds for the Main Content Slide transition to Occur
 - Setting this to large values with large quantities of complex content, such as video or sliders may result in jerky transitions

Open External

- Specify a CSS class selector of the component to be toggled using the Joey Launcher.
 - You can have external content only, if Create Main Content is not selected
 - You can have both Main content and External Content when Create Main Content is selected and you specify a class here.
 - NOTE: DO NOT ADD A DOT BEFORE THE CLASS NAME.
 - You can use a CSSBox stack or similar to give a class name to any element that you wish Joey to reveal

Joey – Scroll Content

Reveal Speed

- The time in milliseconds for the Main Content Slide transition to Occur
 - Setting this to large values with large quantities of complex content, such as video or sliders may result in jerky transitions

Interval

- The time in milliseconds between samples taken of the page scroll position
 - Setting this to a low value will improve sensitivity but may scrolling performance of complex pages.
 - Setting to too high a value may mean that some scroll content that is only set to display for a small range may be missed.

Content

- Show between
 - Only show Scroll Content between the values specified in the Top and Bottom settings
- Hide between
 - Only hide Scroll Content between the values specified in the Top and Bottom settings

Units

- Either absolute **pixels** or as a **percentage** of the total page content height

Important:

If you want Scroll Content to appear as a particular element of your page comes in to view, then always use percentage units. If the browser window is resized, Joey recalculates the absolute positions of the scroll trigger and scroll content will appear at the same relative position on the page.

Pixel units are good for things such as hiding or showing scroll content as the page is initially scrolled but **be aware** the page height in pixels will be different for different browser widths. If you want to show content at a particular point down the page, always use percentage units.